

Edith - crochet bonnet for small people



A vintage inspired crochet design for babies by designer Sidsel Sangild. Edith is a cute bonnet for small people, made in our soft Anina yarn. Pattern uses US crochet terms.

2nd English edition - april 2020 © Filcolana A/S

Materials

50 g Anina from Filcolana colour 334 (Light Blush)
Crochet hook 2,5 mm
Stitch marker or contrast yarn

Sizes

3 mo/62 cl (6 mo/68 cl) 9 mo/72 cl (12 mo/80 cl)

Measurements

Fits head circumference: 38-40 (40-43) 43-46 (46-50)
cm

Gauge

After the first 15 rounds the circle measures 10 cm in diameter.

Abbreviations

Ch: chain stitch

Sl st: slip stitch

Sc: single crochet

Hdc: half double crochet



Special abbreviations

Magic ring: Make a loop of the yarn. Hold the loop between your fingers, insert crochet hook into the loop and pull yarn through to form a new loop on the hook. Yarn over, and pull yarn through the loop on the hook. Make the number of stitches stated in the pattern in the ring and pull the short yarn end to close the ring.

Directions

First make a circle for the back of the bonnet. Then crochet in rows to make side and top of bonnet. On the last round make the edging and the tying bands.

NOTE! All stitches are crocheted in the back loop only unless otherwise stated.

Make a magic ring (see above).

Round 1: Make 8 sc in the ring, and continue in a spiral. Use a stitch marker to mark the beginning of the round and move the marker up after each round.

Round 2: 2 sc in each sc (16 sc)

Round 3: *1 sc, 2 sc in next st*, repeat from * around (24 fm).

Round 4: *2 sc in next st, 1 sc into each of the next 2 sc*, repeat from * to * around (32 sc).

Round 5: *1 sc, 2 sc in next st, 1 sc into each of the next 2 sc*, repeat from * to * around (40 fm).

Round 6: *1 sc into each of the next 4 sc, 2 sc in next st*, repeat from * to * around (48 fm).

Continue in this way increasing 8 sts on every other round making sure the increases are not directly on top of each other.

Continue until the circle measures 12 (13,5) 14 (15) cm in diameter.

Continue in rows:

Row 1: 1 ch (does not count as a st), 1 hdc in each st, to last 4 (5) 5 (5) cm of the round, turn.

Row 2: 1 ch, 1 hdc in each st to last st, 1 hdc in both loops of last st, turn.

Repeat Row 2 until the bonnet measures 12,5 (13,5) 15,5 (16) cm from the middle of the circle to the edge.

Now make short rows to shape the bonnet:

Break yarn. Join yarn again 6 (7) 7 (7) cm from the lower edge (keeping the crochet direction of the pattern), 1 sc in next st, 1 hdc in each st, until the same number of stitches you skipped + 2 stitches remain on the row, 1 sc in next st, 1 sl st in next st, turn.

Next row: 1 ch, skip sl st, 1 sc in next st, 1 hdc in each st until 1 st before sc, 1 sc in last hdc, 1 sl st in sc. Fasten off.

Join yarn again at the edge.

Next row: 1 ch, 1 hdc in each st to last st, 1 hdc in both loops in last st, turn.

Repeat this row once more. Do not break yarn.

Edging and tying bands

Using the yarn still attached to the bonnet, ch 60 (the length should be approximately 18 cm). Turn, 1 sl st in the 2nd ch from the hook, 1 sl st in each ch to the edge of the bonnet, 1 sc in each st of the front edge, ch 60. Turn, 1 sl st in the 2nd ch from the hook, 1 sl st in each ch to the edge of the bonnet, 1 sc along the rest of the edge. (3 sc in each "rib" (2 row ends) gives a flat edge). Fasten off and weave in ends.

